



Sample C# Program for Communicating with the TReX and TReX Jr



The following program, written using Visual C# 2008, provides a simple example of how you can send and receive data from the [TReX](#) or [TReX Jr](#) using [Microsoft's visual C#](#) and your computer's serial port. It sends the TReX a “get signature” command when the **Get Signature** button is pressed and displays the response from the TReX in the text box.

The `sendCommandPacket` method is a simplified version of the one used by the [TReX Configurator utility](#) (297k zip).

You can download the project files here: [trex.zip](#) (60k zip). Don't forget to configure the `serialPort1` object's `portName` property for the COM port to which your TReX or TReX Jr is connected.



Sample C# TReX program: configuring the SerialPort object.

```

1  using System;
2  using System.Windows.Forms;
3
4  namespace TReX
5  {
6      public partial class Form1 : Form
7      {
8          int deviceNum = 7; // default device number for the TReX and TReX Jr
9          bool serialEcho;   // does the TReX echo everything you transmit? (true for RS-232)
10         byte[] buffer;      // array to hold our command packets and received data
11
12         public Form1()
13         {
14             InitializeComponent();
15             buffer = new byte[32];
16         }
17
18         private bool sendCommandPacket(byte[] packet, int sendBytes, int readBytes, ref string str)
19         {
20             /* This function transmits the specified command packet and then waits to receive
21              * the specified number of bytes in response. Bytes to transmit are provided via the
22              * 'packet' array, and received bytes are stored in the 'packet' array.
23              * It blocks execution until the desired number of bytes have been received from the
24              * the TReX or until the serial read times out (150 ms).
25              * packet - an array of bytes to transmit to the TReX; when the function is through,

```

```

26      *      this array will contain any bytes received from the TReX, so the size of
27      *      this array must be greater than or equal to Max(sendBytes, readBytes)
28      *      sendBytes - the number of bytes in the command packet
29      *      readBytes - the number of bytes to try to receive from the TReX in response
30      *      str - a string that contains information about what was sent and received;
31      *      used for debugging/feedback purposes
32      */
33
34      int i;
35      str = "";
36
37      try
38      {
39          // if there are any unread bytes in the read buffer, they are junk
40          // read them now so the buffer is clear to receive anything the TReX
41          // might send back in response to the command
42          while (serialPort1.BytesToRead > 0)
43              serialPort1.ReadByte();
44
45          str += " TX={ ";
46          if (expandedProtocolCheckBox.Checked)
47          {
48              for (i = sendBytes - 1; i >= 0; i--)
49                  packet[i + 2] = packet[i];
50              packet[0] = 0x80;
51              packet[1] = (byte)deviceNum;
52              packet[2] -= 0x80; // clear MSB of command byte
53              sendBytes += 2;
54          }
55
56          for (i = 0; i < sendBytes; i++)
57              str += packet[i].ToString("X2") + " ";
58          serialPort1.Write(packet, 0, sendBytes);
59          if (serialEcho)
60          {
61              str += "; Echo={ ";
62              for (i = 0; i < sendBytes; i++)
63                  str += serialPort1.ReadByte().ToString("X2") + " ";
64          }
65          str += "; RX={ ";
66          for (i = 0; i < readBytes; i++)
67          {
68              packet[i] = (byte)serialPort1.ReadByte();
69              str += packet[i].ToString("X2") + " ";
70          }
71          str += "}";
72      }
73
74      catch (Exception)
75      {
76          str += " *TIMEOUT*";
77          return false;
78      }
79
80      return true;
81  }
82
83
84  private void signatureButton_Click(object sender, EventArgs e)
85  {
86      try
87      {
88          logTextBox.Text = "";
89          serialPort1.Open();
90          buffer[0] = 0xFF;
91          serialPort1.Write(buffer, 0, 1); // send the null command
92          try
93          {
94              int data = serialPort1.ReadByte(); // look for an echo
95              if (data == 255)
96                  serialEcho = true; // we get here if we are using RS-232
97          }
98          catch (TimeoutException)
99          {
100              serialEcho = false; // we get here if we are using TTL serial
101          }
102
103          // read the device signature
104          string str = "";
105          buffer[0] = 0x81;
106          if (!(sendCommandPacket(buffer, 1, 7, ref str)))
107              logTextBox.Text += "failure\r\n" + str;
108          else

```

```
109         {
110             logTextBox.Text += "" + str + "\r\n";
111             for (int i = 0; i < 7; i++)
112                 logTextBox.Text += (char)buffer[i];
113         }
114     }
115     catch (Exception)
116     {
117         logTextBox.Text += "Exception!";
118     }
119     if (serialPort1.IsOpen)
120         serialPort1.Close();
121 }
122 }
123 }
```

Related products



[Pololu TReX Dual Motor Controller DMC01](#)



[Pololu TReX Jr Dual Motor Controller DMC02](#)